

## BREA BEAD WORKS

### FOREVER YOURS BRACELET

*circular right-angle weave*



#### MATERIALS

- ▷ 4mm bicone crystal; color A [12 qty]
- ▷ 4mm bicone crystal; color B [6 qty]
- ▷ 4mm bicone crystal; color C [6 qty]
- ▷ 6mm bicone crystal [8 qty]
- ▷ 8mm bicone crystal [2 qty]
- ▷ 11° seed bead [1 color]
- ▷ 2mm tubular crimp bead [2 qty]
- ▷ Clasp of your choice
- ▷ Fireline thread; 6 lb
- ▷ Flexible beading wire; .015" dia [2 feet]

#### TOOLS

- ▷ Beading needle; size 12
- ▷ Wire Cutter
- ▷ Crimping plier
- ▷ Scissors



Fig. A



Fig. B




Fig. C





Fig. D

**1.** Thread a needle on 4 feet of Fireline thread. String on six 11° seed beads and pass thread through all seed beads to form a loop (Fig. A). Make sure to leave 6" of tail thread. Tie a square knot and pass thread through neighboring bead on left (Fig. B).


**2.** String on 6mm bicone, two 11° seed beads, 4mm bicone A, two 11° seed beads, and 6mm bicone. Form loop by passing thread through center seed bead and then through neighboring seed bead on left (Fig. C).

**3.** String on 6mm bicone, two 11° seed beads, 4mm bicone A, and two 11° seed beads. Pass thread through 6mm bicone already in place, center seed bead, and neighboring seed bead on left (Fig. D).

Repeat this step all around.




**4.** To finish this round, pass thread through 6mm bicone already in place. String on two 11° seed beads, 4mm bicone A, and two 11° seed beads. Pass thread through the other 6mm bicone and center seed bead. Prepare for third round by passing thread back up through 6mm bicone, two 11° seed beads to the left and out through 4mm bicone.





**5.** String on two 11° seed beads, 4mm bicone B, and two 11° seed beads. Pass thread through left 4mm bicone A.

Repeat this step all around.




**6.** End threads by tying half-hitched knots in at least three locations. Do the same for the tail thread.




**7.** Cut 1 foot of flexible beading wire and string it through a outer 4mm bicone B. Center bead on wire. On each wire, string on three 11° seed beads, 4mm bicone C, and five 11° seed beads. Pass both wires through an 8mm bicone.

**8.** On each wire, string on seven 11° seed beads, 4mm bicone A, and five 11° seed beads. Pass wires through a 4mm bicone C using the ladder stitch (from opposite ends of bicone).



**9.** On each wire, string on seven 11° seed beads. Pass both wires through a 6mm bicone.



**10.** With wires together; string on a 11° seed bead and a 4mm bicone A. Attach toggle clasp using a 2mm tubular crimp bead. Crimp securely and trim excess wires.

Repeat steps 7 through 10 to finish other side of bracelet.

